

[Supporting Software]

NovalCT V5.4.2 or later

[New Features]

1. Introduced a new dehumidification feature.

[Improvements]

1. Added an optical enhancement mode in the LCD to improve transmission quality.
2. Enhanced optical port compatibility to support the Eoptolink optical modules.
3. Improved the issue of screen flickering when switching sources or changing resolutions.
4. Optimized the logic for saving brightness during automatic brightness adjustment.
5. Enhanced the communication mechanism for 100 Mbps networks.

[Changes]

N/A

[Bug Fixes]

1. Fixed the issue causing a black screen on OPT 2 output and the inability to read back receiving card parameters.
2. Fixed the issue where the test pattern became unresponsive after exiting calibration when there was no active source.
3. Fixed issues related to the sending card configuration files.
4. Fixed the issue with abnormal mapping when cascading sending cards.

[Notes]

N/A